


# Printing to PowerRIP 2000 from FreeHand 8.x using Win 95/98

**Note:** It is assumed that a FreeHand file is on the screen and ready to be printed.

## Step 1:

### File>Printer Setup

The Printer Setup dialog will display.  
Select your printer.




## Step 2:

### File>Print

The Print dialog will display.  
Select Print to File


**Note:**FreeHand sends header information along with the PostScript file when the print command is executed. This creates various PostScript errors. Print to File circumvents this header information and allows you to print FreeHand files to your printer. For ease of operation create a new folder on your hard drive to house your FreeHand PostScript files.



## Step 3:

### Select Use PPD.

The **Select PPD** dialog will display.  
Go to the **PowerRIP 2000HP folder>PPD folder>US folder** and select the PPD for your printer.  
Click **Open**.




# Printing to PowerRIP 2000 from FreeHand 8.x using Win 95/98 (Cont)

## Step 4:

The **Print** dialog will display.  
The name of your printer will display to the right of Use PPD.


Make sure **Composite** is selected.  
Click **Setup**.



## Step 5:


The **Print Setup** dialog will display.  
**Separation** tab.

Make sure **Composite** is selected.



## Step 6:


**Imaging** tab.  
Select **Split Complex Paths**.  
Click **OK**.



# Printing to PowerRIP 2000 from FreeHand 8.x using Win 95/98 (Cont)


## Step 7:

The **Print** dialog will display.  
Click **Properties**.  
The **Properties** dialog will display.  
**Paper** tab.  
Select the appropriate **Paper Size**.




## Step 8:

**Graphics** tab.  
Select the appropriate **Resolution**.




## Step 9:

**Device Options** tab.  
Select the features appropriate for your needs.  
This is a scrollable dialog. Do not leave any of  
the features as Printer default. Define every  
feature.  
Click **OK**. Click **OK**.



## Step 10:


The **Print to File** dialog will display.  
Navigate to the folder you want to save the  
file in.  
Give your file a name.  
Click **Save**.  
The PostScript file will save to the folder.



# Printing to PowerRIP 2000 from FreeHand 8.x using Win 95/98 (Cont)


## Step 11:

Print the PostScript file.  
Launch PowerRIP 2000.  
(Start>Programs>PowerRIP 2000 HP>  
Power 2000 HP)  
Maximize PowerRIP 2000.



## Step 12:

Go to **File>Print PostScript File**.  
The **Open** dialog will display.  
Navigate to the folder you saved your file  
in.  
Highlight the file.  
Click **Open**.



## Step 13:

The **Configure Document Specs** dialog will  
display.  
Make sure the correct printer is selected in  
Printer.  
Make sure the correct LPT port is selected  
in On.  
Select **Use Print Manager**.  
Select **Document Default Settings**.  
Click **OK**. The file will process and print.

