


Printing to PowerRIP 2000 from FreeHand 9.x using Win 95/98

Note: This document assumes that a FreeHand file is on the PC screen and is ready to be processed and printed.

Step 1:

File>Printer Setup

The Printer Setup dialog will display.
Select your printer.
Click **OK**.




Step 2:

File>Print

The **Print** dialog will display.

Select Print to File


Note: Freehand sends header information along with the PostScript file when the print command is executed. This creates various PostScript errors. Print to File circumvents this header information and allows you to print FreeHand files to your printer. For ease of operation create a new folder on your hard drive to house your FreeHand PostScript files.



Step 3:

Select Use PPD.

The **Select PPD** dialog will display.
Go to the **PowerRIP 2000NEC folder>PPD folder>US folder** and select the PPD for your printer.
Click **Open**.




Printing to PowerRIP 2000 from FreeHand 9.x using Win 95/98 (Cont)

Step 4:

The **Print** dialog will display.
The name of your printer will display to the right of Use PPD.


Make sure **Composite** is selected.
Click **Setup**.



Step 5:


The **Print Setup** dialog will display.
Separation tab.

Make sure **Composite** is selected.



Step 6:

Imaging tab.
Select **Split Complex Paths**.
Click **OK**.



Printing to PowerRIP 2000 from FreeHand 9.x using Win 95/98 (Cont)

Step 7:


The **Print** dialog will display.

Click **Properties**.

The **Properties** dialog will display.

Paper tab.


Select the appropriate **Paper Size**.



Step 8:

Graphics tab.

Select the appropriate **Resolution**.



Step 9:


Device Options tab.

Select the features appropriate for your needs.

The Printer Features include: Separations, Color to Monochrome Mapping, Paper Type, and Screening.

Click **OK**.

Click **OK**.



Printing to PowerRIP 2000 from FreeHand 9.x using Win 95/98 (Cont)

Step 10:


The **Print to File** dialog will display.

Navigate to the folder you want to save the file in.

Give your file a name.

Click **Save**.

The PostScript file will save to the folder.




Step 11:

Print the PostScript file.

Launch PowerRIP 2000.

(Start>Programs>NEC SuperScript PowerRIP>NEC SuperScript Power.

Maximize PowerRIP 2000.



Step 12:


Go to **File>Print PostScript File**.

The **Open** dialog will display.

Navigate to the folder you saved your file in.

Highlight the file.

Click **Open**.



Step 13:

The **Configure Document Specs** dialog will display.

Make sure the correct printer is selected in Printer.

Make sure the correct LPT port is selected in On.

Select **Use Print Manager**.

Select **Specify Settings**.

Select the appropriate settings.

Click **OK**. The file will process and print.

