

# Printing to PowerRIP 2000 using PageMaker 6.5

Using Server/Standalone Macintosh, OS 8.6 or later

**Note:** - The following directions are for LaserWriter 8.7 and AdobePS 8.7.

- Desktop Print Monitor and Desktop Print Spooler must be active in the Extension Manager. Sharing should be turned on in both the server and client Macintoshes.

This document assumes that PowerRIP 2000 has been launched and Open Printer has occurred. It also assumes that a PageMaker file is on the Macintosh screen and is ready to be processed and printed.

## LaserWriter 8.7

### Step 1:

#### Chooser

In the Chooser highlight **LaserWriter 8.7**.  
Highlight your printer.  
Click **Create**.

**Note:** The first time you select the PPD it will say *Create*. All future selections in the Chooser will say *Setup*.

Click **Select PPD**.  
Highlight the appropriate PPD for your printer and click **Choose**.  
Close the Chooser  
A Desktop Printer will be created.

### Step 2:

Go to **File>Print**.

The PageMaker print dialog will display.  
Make sure the PPD is correct and the correct printer is defined in Printer:




### Step 3:

Click **Features**.

Select the appropriate Features. For an in-depth discussion of the Features for your printer see Appendix 4 of the PowerRIP 2000 manual.


**Note:** This is a scrollable window.



### Step 4:

Click **Color**.

Make sure **Composite** is selected.



# Printing to PowerRIP 2000 using PageMaker 6.5

Using Server/Standalone Macintosh, OS 8.6 or later (Cont)

## Step 5:

Click **Options**.

Select **Normal** in Send image data.

Click **Print**.

The file will process and print.



## AdobePS 8.7

### Step 1:

**Chooser**

In the Chooser highlight **AdobePS 8.7**.

Highlight your printer.

Click **Create**.

*Note: The first time you select the PPD it will say Create. All future selections in the Chooser will say Setup.*

Click **Select PPD**. Highlight the appropriate PPD for your printer and click **Select**.

Close the Chooser.

A Desktop Printer will be created.

### Step 2:

Go to **File>Print**.

The PageMaker print dialog will display.

Make sure the PPD is correct and the correct printer is defined in Printer:




### Step 3:

Click **Features**.

Select the appropriate Features. For an in-depth discussion of the Features for your printer see Appendix 4 of the PowerRIP 2000 manual.


*Note: This is a scrollable window.*



### Step 4:

Click **Color**.

Make sure **Composite** is selected.



# Printing to PowerRIP 2000 using PageMaker 6.5

Using Server/Standalone Macintosh, OS 8.6 or later (Cont)

## Step 5:

Click **Options**.

Select **Normal** in Send image data.

Click **Print**.

The file will process and print.

The screenshot shows the Print dialog box with the Options tab selected. The dialog is divided into several sections:

- TIFFs/Images:** Send image data: **Optimized subsampling**; Data encoding: **Send binary image data**.
- PostScript:** Download fonts: **PostScript and TrueType**;  Use symbol font for special characters;  Include PostScript error handler;  Write PostScript to file: [ ] Save as...;  Normal;  EPS;  For prepress;  Page independence;  Extra image bleed;  Launch post-processor.
- Prior communication:**  Query printer for font and memory information.

Buttons on the right side of the dialog include: **Print**, **Cancel**, **Document**, **Paper**, **Options**, **Color**, **Features**, and **Reset**.